



MyDiag diagnostic

This page gives an overview of the MyDiag diagnostic set implemented in the ESMValTool. It is intended as a template for adding new diagnostics to the tool.

The following points are covered,

- Files to modify
- How to get a certain version (revision) of the code and create a predefined test plot

Files to modify

All paths in the following are relative to the root folder of the ESMValTool.

- `nml/namelist_MyDiag.xml`:

Global flags, diagnostics to do, and models that shall be evaluated by those diagnostics are specified here. Each `<diagnostic>` entry must refer to a script in the folder `diag_scripts/`, complemented by a variable and the corresponding (input) field type. Data that shall be evaluated by specific diagnostics only may be added with `<model>` specifiers to the respective diagnostics. See here for a more comprehensive [list of namelist XML tags](#).

- `nml/cfg_MyDiag/cfg_MyDiag.ncl`:

This file contains specific control parameters in NCL syntax for the diagnostic script `diag_script/MyDiag.ncl`. They are specified as attributes of the variable `diag_script_info`. All `cfg_*` files for a diagnostic set need to be in the same folder, as specified by the `<diag_script_cfg_dir>` entry of `nml/namelist_MyDiag.xml`.

- `var_att/MyVar.att`:

Variable specific parameters are defined here in NCL syntax, as attributes of the variable `var_att_info`. Derived variables require a `calculate` function. Here temperature at 200 hPa is extracted from the CMIP5 `ta` variable and defined as `MyVar`.

- `diag_script/MyDiag.ncl`:

This is the actual diagnostic routine, as specified by a `<diag_script>` entry in `nml/namelist_MyDiag.xml`. It makes use of the function `contour_map` in `plot_scripts/contour_map.ncl` for plotting, and other general functions (e.g. for fetching data, writing NetCDF output, time averaging). Please look into the code ...

- `doc/MASTER_authors-refs-acknow.txt`:

This is the central lookup table for references & acknowledgements that might be selected within the `plot_type` routines.

The following files allow project specific control, but in general do not need to be modified when implementing a new diagnostic.

- `interface_scripts/projects.py`:

This routine controls the interpretation of the elements in each `<model>` entry of `nml/namelist_MyDiag.xml`. This is controlled by the first ("project") element in each `<model>` entry.

- `diag_scripts/lib/ncl/style.ncl`:

This routine defines project specific settings for annotation, line colors, dash patterns etc. It is chosen via the `diag_script_info@styleset` entry in `nml/cfg_MyDiag/cfg_MyDiag.ncl`.

MyDiag test suite

The software requirements for running the test suite are listed on the [Getting started](#) page.

The test case is located in revision 1140 of the [trunk](#) of the repository. To check out and run it, follow the instructions below. Note that commands to be issued are written highlighted while general instructions are written as normal text.

1. `svn checkout --username <USERNAME> -r 1140 https://svn.dlr.de/ESM-Diagnostic/source/trunk@1140 ESMValTool_r1140`
2. `cd ESMValTool_r1140`

OR alternatively, if starting from a tar-file (revision number might be different from r1140):

1. `tar xvf ESMValTool_r1140.tar`
2. `cd ESMValTool_r1140`

3. In the `nml/namelist_MyDiag.xml`-file, update the following tags with proper paths,

```
<wrk_dir> - path to dir working dir
<plot_dir> - path to where output figures are placed
<climo_dir> - path to where intermediate NetCDF files are written
```


4. In the `nml/namelist_MyDiag.xml`-file, update the models listed in the `<MODELS>` section with CMIP5 data sets available on your file system.

The syntax for each line is,

```
<project> <model> <MIP_table> <experiment> <ensemble_member> <start_year> <end_year> <path to file>
```

5. Run MyDiag diagnostic with `main.py nml/namelist_MyDiag.xml`

The following figure should have been produced in the `MyDiag` subfolder of your `<plot_dir>`:



Now browse the files listed in the first section and modify them according to your needs.

In general it is a good idea to consult also other diagnostic sets that might serve as a better template for your diagnostic.

Please report anything that needs to be changed to klaus-dirk.gottschaldt@dlr.de

For further documentation on usage of the tool, see the [ESMValTool Wiki](#).